



Defaulting a Printer


Version 8

<https://youtu.be/xofYSBH46tA>

You may find you want to change the Default Printer settings.

This guide will show you how to set a default printer, design and paper size for all document print outs or specific document types. There are many areas we can set default designs for.


1. Starting from the main screen in Retail Pro, click the OPTIONS button on the top menu and then the W/S Preferences on the side menu.




2. Next, choose Printing on the side menu and then select Area.

Active	Printer	Design	Copies	Collate	Preview	Paper Size
<input type="checkbox"/>	ABS PDF Driver v400		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	Fax		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	HP LaserJet P3010 Series UI		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	Microsoft XPS Document V		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	Send To OneNote 2010		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	Star TSP100 Cutter (TSP143)		1	<input type="checkbox"/>	<input type="checkbox"/>	


- Here you can choose which print area you would like to set the default designs for IE: All Receipts, All SOs, All Vouchers, etc. All Receipts allows you to set the default printer and design for every receipt type.



- In this example we will use All Receipts and set the defaults. If we are using this we need to check off the Override Individual Document Settings Included in this Area. If this is not checked the settings for each individual area will take over.



- Next, we can set the default printer by choosing the “Active” box next to the printer.



- Then, choose the design you would like to be the default and set the paper size for the printer.

Printers

Active	Printer	Design	Copies	Collate	Preview	Paper Size
<input type="checkbox"/>	ABS PDF Driver v400		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	Fax		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	HP LaserJet P3010 Series UI		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	Microsoft XPS Document V		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	Send To OneNote 2010		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input checked="" type="checkbox"/>	Star TSP100 Cutter (TSP143	Big Hairy Dog 40 Col	1	<input type="checkbox"/>	<input type="checkbox"/>	

The design dropdown menu for the Star TSP100 Cutter (TSP143) is open, showing the following options:

- Big Hairy Dog 40 Col
- 40 Col
- 40 Col Copy
- 40 Col Shift4
- 40 Col Shift4 EMV
- Epson Slip
- Epson Slip Copy
- Gift

Printers

Active	Printer	Design	Copies	Collate	Preview	Paper Size
<input type="checkbox"/>	ABS PDF Driver v400		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	Fax		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	HP LaserJet P3010 Series UI		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	Microsoft XPS Document V		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input type="checkbox"/>	Send To OneNote 2010		1	<input type="checkbox"/>	<input type="checkbox"/>	
<input checked="" type="checkbox"/>	Star TSP100 Cutter (TSP143	Big Hairy Dog 40	1	<input type="checkbox"/>	<input type="checkbox"/>	72mm x Receipt

- Towards the bottom of the screen, there are 4 check boxes. These allow you to change the Printer, Design, Copies and to be able to preview a document. This lets you set defaults, but still be able to choose a different printer or design at the time of printing.

Allow change at time of printing

Printer Copies

Design Preview

- Finally, Save your change on the side menu and test.
- You can repeat this process for each different print area, choosing the Printer and desired Design Options.